

TRIO Table Mic Array Release Notes

Release Version: 1.09

Release Date: 6/15/2015

New Features and Functions

- Interoperability Support for AV Bridge MATRIX PRO

Fixed Issues

- N/A

Known Issues

- N/A

Interoperability Testing and Findings

- Same as previous release.

Backward Compatibility

- Same as previous release.

User Notes

- Microphones must be updated through the Vaddio Mixer/Amp and Vaddio Loader.

Vaddio TRIO Table Mic Array Firmware Update Instructions For Version 1.09

Requirements:

- USB to Serial Adapter
- 1001 DB9 to RJ-45 Adapter
- Latest version of Vaddio Loader program from [Vaddio Support](http://support.vaddio.com) website
http://support.vaddio.com/resources#cat_3 (Scroll down to Vaddio Loader at bottom of page)


Step-By-Step Process:

1: Download and save software from here: http://support.vaddio.com/resources#cat_3 (Scroll down to Software Updates – choose appropriate software file for the update needed.)

File name: TRIO Table Mic Array Update V1.09


2) Connect the Mixer/Amp to the PC from the RS-232 port into the DB9 to RJ-45 adapter and plug that into the USB to serial cable.

3) Open up the Vaddio Loader and select audio devices, then select Mixer/Amp




4) Under file, select the COM port your USB to serial adapter is using.

5) Now, let's check the firmware version we're currently on.
Click on file > serial commands





6) Check ASCII Command and type in a question mark (?), you should get a response similar to what is shown below.



7) At this point your device is ready to load the firmware.

If you need more instructions: Select File – Instructions and a window will pop open with more details to reference.

Please note: the examples shown below are for the EasyMic Table MicPOD, this software update uses the same instructions for the TRIO Table Mic Array




8) Unplug the Mixer/Amp and flip dip switch 8 up. Let it start up for about 15 seconds.

9) Plug in one of your microphones. **ONLY ONE MICROPHONE AT A TIME!** It does not matter which port you plug the mic into.


10) In the dropdown menu where we selected Mixer/Amp, select the microphone you're updating (ceiling or table top mic)

Please note: the examples shown below are for the EasyMic Table MicPOD, this software update uses the same instructions for the TRIO Table Mic Array – you will select the EasyMic Table MicPOD to be used for the TRIO update.




11) Select your load file (select the firmware you downloaded back in Step 1)

File name: TRIO Table Mic Array Update V1.09




12) Hit Start




Updating Mode:

- The squares in the corner should start to flash and the progress bar on the bottom should start to fill in.
- The power LED on the unit should also begin to blink, as well as the mute light on the mic.



**In approximately 10 minutes, the Vaddio Loader should tell you that your mic is updated. Repeat steps 9-12 for the second mic, if you have multiples.



PLEASE NOTE:

If you have any questions call Tech Support at Vaddio. 763.971.4428 or 1-800-572-2011.